



2653 Auburn Road,  
Auburn Hills, MI 48326  
[www.testittoday.com](http://www.testittoday.com)  
[info@absolutelabs.net](mailto:info@absolutelabs.net)  
T+ 877.343.5227  
T+ 248.844.9000

## AIR QUALITY MOLD TEST KIT

**RESULTS IN 2 -3 BUSINESS DAYS** upon receipt of samples

### DIRECTIONS

Instructional video: <https://tinyurl.com/moldinair>

1. Close exterior doors and windows 24 hours prior to, and during, air sampling. Normal entry and exit is fine.
2. Optional: Turn the HVAC thermostat fan on 5 minutes prior to, and during, air sampling; this provides a more uniform air sample. Note: do not run fan if severe contamination is suspected.
3. Place pump 2-5' above the ground. Remove blue plug from base of spore trap, insert plastic tip at the base of spore trap into the rigid tube on top of the pump.
4. Remove top sticker from the spore trap. Note: keep sticker to reseal the spore trap once the sample is complete.
5. Press the start button. The pump will automatically stop after 5 minutes. Only run for 5 minutes!
6. Remove spore trap and reseal the openings using the saved sticker and blue plug.
7. **Important:** Note the serial number on the spore trap on the form below and describe the corresponding location. (e.g. serial no.: 2056409 – site description: 2<sup>nd</sup> floor master bedroom). Place sample into sealable bag.
8. For each additional air sample repeat steps 3-10, placing in the air pump in living areas of interest.
9. An exterior reference sample taken outside near the property is **required** for interpretation.
10. Fill out the remainder of the form\* and **mail all kit contents back**. *\*A signature is required for analysis.*

### REPORTING INFORMATION - HVAC: On Off

1. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
2. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
3. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
4. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
5. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
6. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_
7. Serial no.: \_\_\_\_\_ Site description: \_\_\_\_\_

Site address or project no.: \_\_\_\_\_

Sampler's name: \_\_\_\_\_ Date taken: \_\_\_\_\_

Phone no.: \_\_\_\_\_ Special notes: \_\_\_\_\_

Email(s) for results: \_\_\_\_\_

Relinquished by (signature\*): \_\_\_\_\_ Date: \_\_\_\_\_ Time: \_\_\_\_\_

**RUSH SAMPLES - SAME DAY:** \$15/sample (must be received before 12PM EST M-F)

**RUSH SAMPLES - NEXT DAY:** \$10/sample (next day results if received M-Th)

Analyze non-fungal allergens: \$20/sample (bacterial clusters, squamous cells, pollen, and insect fragments)

### PAYMENT OPTIONS

1.  My check is enclosed (payable to Absolute Labs, Inc.)

2.  Charge my: MC VISA AMEX DISC ACCOUNT KEEP MY INFORMATION ON FILE

Name: \_\_\_\_\_

Credit card #: \_\_\_\_\_ Exp. date: \_\_\_\_\_

Billing address: \_\_\_\_\_

City, State, Zip: \_\_\_\_\_

3.  Pay online <http://www.testittoday.com/product/air-quality-mold-test/> - Order no.:

4.  Cash – in person only

*\*By signing this form the client agrees to the terms and conditions posted on [testittoday.com](http://testittoday.com) and [absolutelabs.net](http://absolutelabs.net).*

### LAB USE ONLY

Date received: \_\_\_\_\_ Received by: \_\_\_\_\_ Lab technician: \_\_\_\_\_

Time received: \_\_\_\_\_ Lab file no.: \_\_\_\_\_ Date analyzed: \_\_\_\_\_